



Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

Int 21H, AH=0EH

Version

1 and higher

Brief

SELECT DEFAULT DRIVE

Family API

[DosSelectDisk](#)

Input

```
AH = 0Eh
DL = new default drive (00h = A:, 01h = B:, etc)
```

Return

AL = number of potentially valid drive letters

Notes

under Novell NetWare, the return value is always 32, the number of drives that NetWare supports

under DOS 3.0+, the return value is the greatest of 5, the value of LASTDRIVE= in CONFIG.SYS, and the number of drives actually present on a DOS 1.x/2.x single-floppy system, AL returns 2 since the floppy may be accessed as either A: or B: otherwise, the return value is the highest drive actually present

DOS 1.x supports a maximum of 16 drives, 2.x a maximum of 63 drives, and 3+ a maximum of 26 drives

under Novell DOS 7, this function returns the correct LASTDRIVE value even when the undocumented LASTDRIVE=27..32 directive was used in CONFIG.SYS

“parse FCB” (see AH=29h) can be used to determine whether a drive letter is valid

See also

AH=19h,AH=3Bh,AH=DBh

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

DOS API	
Process manager	INT 20H, INT 21H : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H
File manager	INT 25H, INT 26H, INT 21H : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH
Character Device I/O	INT 29H, INT 21H : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH
Signals	INT 23H, INT 24H, INT 21H : 3300H, 3301H, 3302H
Memory manager	INT 21H : 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H
Date and Time	INT 21H : 2AH, 2BH, 2CH, 2DH
Misc	INT 21H : 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H
NLS	INT 21H : 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H
Devices	INT 21H : 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H
Network	INT 21H : 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek

osFree Macro Library

Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

Family API

DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:

<https://cocorico.osfree.org/doku/> - **osFree wiki**

Permanent link:

<https://cocorico.osfree.org/doku/doku.php?id=en:docs:dos:api:int21:0e&rev=1714203724>

Last update: **2024/04/27 07:42**

