

# Windows 3.1 SETUP.INF Complete Reference

## Introduction

SETUP.INF is the master configuration file that controls every aspect of Windows 3.1 installation. This comprehensive reference documents all sections, keys, and installation processes based on the original Windows Resource Kit documentation.

## Installation Process Overview

The Windows installation follows this precise sequence:

### Phase 1: Initialization

1. Read [setup] section for help file location
2. Process [data] section for system requirements and defaults
3. Initialize disk definitions from [disks] and [oemdisks]
4. Load dialog text from [dialog] section

### Phase 2: File Copying

1. Copy core Windows files from [windows] section
2. Copy system files from [windows.system] section
3. Copy 386-specific files from [windows.system.386]
4. Install display drivers from [display] section
5. Install keyboard drivers from keyboard sections
6. Install mouse drivers from pointing device sections
7. Copy network components if selected
8. Install fonts based on display resolution

### Phase 3: Configuration

1. Update INI files based on [ini.upd.patches] and [ini.upd.31]
2. Create Program Manager groups
3. Run post-installation programs from [run] section

### Phase 4: Finalization

1. Process [blowaway] section to mark installation end
2. Clean up temporary files

## General Installation Sections

### [setup] Section

Defines the Setup help file location.

### Format:

```
[setup]
help=filename.hlp
```

### Parameters:

Parameter	Value	Description
-----	----	-----
help	setup.hlp	Specifies the help file for Setup program

### Example:

```
[setup]
help=setup.hlp
```

### [run] Section

Specifies programs to execute after Setup completion.

### Format:

```
[run]
"program_name"
```

### Parameters:

Parameter	Description
-----	-----
program_name	Executable to run after installation

### Example:

```
[run]
"control" ; Runs Control Panel after Setup
```

### [dialog] Section

Contains all text strings displayed in Setup dialog boxes.

### Complete Standard Entries:

```
[dialog]
caption = "Windows Setup"
exit = "Exit Windows Setup"
title = "Installing Windows 3.1"
```

```
options = "In addition to installing Windows 3.1, you can:"
printwait = "Please wait while Setup configures your printer(s)..."
copywait = "Welcome to Microsoft Windows 3.1 ! ..."
```

## [winexec] Section

Provides core file information for Windows Mode Setup.

### Complete Standard Entries:

```
[winexec]
execstd= "dosx.exe" ; MS-DOS Extender for standard mode
execcmd= " krnl286.exe lb /q:" ; Command and switches for kernel
exechem= "xmsmmgr.exe" ; Extended memory manager for Setup
himemcmd= "" ; Switches for HIMEM.SYS
Krnl386= 2:krnl386.exe ; Kernel for 386 enhanced mode
Krnl286= 2:krnl286.exe ; Kernel for standard mode
dosx= 2:dosx.exe ; Disk location for DOSX.EXE file
```

## [data] Section

Defines system requirements, defaults, and installation parameters.

### Disk Space Requirements (in bytes):

```
[data]
netadmin= 16000000 ; 16.0 MB
netadminupd= 16000000 ; 16.0 MB
upd2x386full= 10500000,8000000 ; 10.5 MB, 8.0 MB
upd2x386net= 300000 ; 0.3 MB
upd3x386full= 5500000,5000000 ; 5.5 MB, 5.0 MB
upd3x386net= 300000 ; 0.3 MB
upd2x286full= 9000000,6500000 ; 9.0 MB, 6.5 MB
upd2x286net= 300000 ; 0.3 MB
upd3x286full= 5500000,5000000 ; 5.5 MB, 5.0 MB
upd3x286net= 300000 ; 0.3 MB
new386full= 10500000,8000000 ; 10.5 MB, 8.0 MB
new286full= 9000000,6500000 ; 9.0 MB, 6.5 MB
new386net= 300000,300000 ; 0.3 MB, 0.3 MB
new286net= 300000,300000 ; 0.3 MB, 0.3 MB
```

### System Configuration Parameters:

```
startup= WIN.COM ; File referred to when starting
Windows
defdir= C:\WINDOWS ; Default directory for installation
short name= Windows ; Default based on [language]
welcome= "Windows 3.1" ; Welcome message
```

```
deflang= enu ; Default language based on  
[codepage]  
defxlat= 437 ; Default code page  
defkeydll= usadll ; Default based on [keyboard.tables]  
register= "regedit /s /u setup.reg" ; Default file for registration  
database  
tutor= "wintutor.exe" ; Tutorial to run at end of  
installation  
NetSetup= FALSE ; TRUE allows only SETUP /N  
MouseDrv= TRUE ; Setup uses the mouse  
Version= "3.1" ; Current Windows version
```

## [disks] and [oemdisks] Sections

Define all installation disks and their properties.

### Format:

```
disk_number= path, "disk_name", disk_tag
```

### Field Definitions:

Field	Description
----	-----
disk_number	Single character 1-9 or A-Z (0 reserved for Setup directory)
path	Disk path ( "." = same drive as Windows Setup disks)
disk_name	Disk label in quotes
disk_tag	Volume name for disk verification

### Complete Standard Entries:

```
[disks]  
1=. , "Microsoft Windows 3.1 Disk #1", disk1  
2=. , "Microsoft Windows 3.1 Disk #2", disk2  
3=. , "Microsoft Windows 3.1 Disk #3", disk3  
4=. , "Microsoft Windows 3.1 Disk #4", disk4  
5=. , "Microsoft Windows 3.1 Disk #5", disk5  
6=. , "Microsoft Windows 3.1 Disk #6", disk6  
  
[oemdisks]  
Z=. , "HP DeskJet Series v2.0 disk (from printer box or contact HP)", diskz
```

## [user] Section

Defines the temporary file containing user and company identification.

## Core File Copying Sections

### [windows] Section

Files copied to WINDOWS directory during MS-DOS Mode Setup.

#### Complete Standard Entries:

```
[windows]
1:setup.hlp
1:setup.inf
3:control.hlp
2:win.src, Net           ; Copied only for Administrative Setup (setup
/a)
1:system.src, Net       ; Copied only for Administrative Setup (setup
/a)
1:winhelp.exe
```

### [windows.system] Section

Files copied to SYSTEM subdirectory.

#### Complete Standard Entries:

```
[windows.system]
1:gdi.exe
1:user.exe
1:win.cnf
1:lzexpand.dll
2:ver.dll
```

### [windows.system.386] Section

386-specific files for SYSTEM subdirectory.

#### Complete Standard Entries:

```
[windows.system.386]
1:cpwin386.cpl
```

## Memory Manager Support Sections

### 386Max Support:

```
[386max]
2:386max.vxd           ; Files copied if system is using 386Max
```

```
2:windows.lod
```

### BlueMax Support:

```
[bluemax]
2:bluemax.vxd          ; Files copied if system is using BlueMax
2:windows.lod
```

### [shell] Section

Defines the Windows shell application.

### Complete Standard Entry:

```
[shell]
progman.exe, "Windows Program Manager"
```

## Display Driver Sections

### Display Driver Components

Windows display drivers require three file types:

- **.DRV file** - Main display driver (e.g., VGA.DRV)
- **Grabber files** - .2GR for standard mode, .3GR for 386 enhanced mode
- **VDD files** - Virtual Display Drivers (VDDx.386) for 386 enhanced mode

### [display] Section Format

```
keyname= driver, description, resolution, 286grabber, logo code, VDD,
386grabber, ega.sys, logo data, optional section
```

### Complete Field Definitions:

Field	Description
keyname	Profile name for driver references in other SETUP.INF sections
driver	Filename of the display device driver
description	Driver description in quotes (appears in Change System Settings dialog)
resolution	Aspect ratio as three comma-separated numbers in quotes
286grabber	Filename of the 286 grabber for standard mode data exchange
logo code	Filename for Microsoft Windows logo code
VDD	Filename for the Virtual Display Driver
386grabber	Filename of the 386 grabber for 386 enhanced mode data exchange

ega.sys	Filename for data determining EGA.SYS driver installation need
logo data	Filename for appropriate Microsoft logo bitmap
optional section	Name of section with additional display driver information

**Important:** Do not change description strings as they are used for upgrade decisions.

### Example Entry for 8514/a Display:

```
8514= 2:8514.drv, "8514/a", "100,120,120", 3:vgacolor.2gr, 2:vga logo.lgo,
2:vdd8514.386, 3:vgadib.3gr, , 2:vga logo.rle, 8514
```

### Optional Display Sections

Available optional sections for display drivers:

```
[v7vga], [vgamono], [8514], [8514s], [tiga1], [tiga2], [v7b], [v7c], [v7d],
[v7t], [v7e], [xgasm], [xgalg], [xgalo]
```

### Optional Section Format:

```
file, destination, ini file, section, OldEntry, NewEntry
```

### Optional Section Field Definitions:

Field	Description
----	-----
file	Optional file to copy (can be null)
destination	Directory for file copy (0: = WINDOWS, 0:system = SYSTEM)
ini file	.INI file to modify (WIN.INI or SYSTEM.INI)
section	Section in .INI file to modify
OldEntry	Entry to remove from .INI file (in quotes, optional)
NewEntry	New entry to add to .INI file (in quotes)

### Example Optional Section:

```
[8514]
, , system.ini, 8514.DRV, "dpi=", "dpi=120"
```

### [.3gr] Font Sections

Define fonts for 386 grabbers that support text/graphics copying from non-Windows applications.

### Available .3gr Sections:

```
[vga.3gr], [vga lo.3gr], [v7vga.3gr], [ega.3gr], [vgadib.3gr], [plasma.3gr],
[herc.3gr], [tiga.3gr]
```

## Example for Video 7 VGA:

```
[v7vga.3gr]
2: CGA40WOA.FON, 2: CGA40850.FON
2: CGA80WOA.FON, 2: CGA80850.FON
2: EGA40WOA.FON, 5: EGA40850.FON
2: EGA80WOA.FON, 2: EGA80850.FON
```

## Font Selection Rules:

- Code page 437 (US default): Copies \*WOA.FON files
- Other code pages: Copies \*850.FON files

## Keyboard and Code Page Sections

### [keyboard.drivers] Section

Maps keyboard driver filenames to short names.

### Complete Standard Entries:

```
[keyboard.drivers]
kbd= 2:keyboard.drv
kbdhp= 2:kbdhp.drv
```

### [keyboard.types] Section

Creates keyboard short names used in [machine] section.

### Format:

```
short_name = "description", DLL_filename
```

### Field Definitions:

Field	Description
----	-----
short_name	Abbreviated descriptor for [machine] section
description	Description in quotes for Change System Settings dialog
DLL_filename	Supporting DLL filename (can be null)

### Complete Standard Entries:

```
[keyboard.types]
t3s0alat= "All AT type keyboards (84-86 keys)",nodll
t1s2at&t= "AT&T '301' keyboard",nodll
```



```
t1s4at&t= "AT&T '302' keyboard",nodll
t4s0enha= "Enhanced 101 or 102 key US and Non US keyboards",nodll
t3s0hp1= "Hewlett-Packard Vectra keyboard (DIN)",nodll
t4s40oliv= "Olivetti 101/102 A keyboard",nodll
t1s0oliv= "Olivetti 83 key keyboard",nodll
t3s10oliv= "Olivetti 86 Key keyboard",nodll
t2s10oliv= "Olivetti M24 102 key keyboard",usadll
t1s42oliv= "PC-XT 83 key keyboard",nodll
t1s0pcxt= "PC/XT -Type keyboard (84 keys)",nodll
```

## [keyboard.tables] Section

Maps DLL short names to disk locations for international language support.

### Complete Standard Entries:

```
[keyboard.tables]
beldll= 2:kdbbe.dll , "Belgian"
bridll= 2:kbduk.dll , "British"
cafdll= 2:kbdfc.dll , "Canadian Multilingual"
dandll= 2:kbdde.dll , "Danish"
dutdll= 2:kbdne.dll , "Dutch"
findll= 2:kbdfi.dll, "Finnish"
fredll= 2:kbdfr.dll , "French"
candll= 2:kbdca.dll , "French Canadian"
gerdll= 2:kbdgr.dll , "German"
icedll= 2:kbdic.dll , "Icelandic"
itadll= 2:kbdit.dll , "Italian"
latdll= 2:kbdla.dll , "Latin American"
nordll= 2:kbdno.dll , "Norwegian"
pordll= 2:kbdpo.dll , "Portuguese"
spadll= 3:kbdsp.dll , "Spanish"
swedll= 2:kbdsw.dll , "Swedish"
swfdll= 2:kbdsf.dll , "Swiss French"
swgdll= 2:kbdsg.dll , "Swiss German"
nodll=, "US"
usadll= 2:kbdus.dll , "US"
usddll= 2:kbdsv.dll , "US-Dvorak"
usxdll= 2:kbdusx.dll, "US-International"
```

## [codepages] Section

Defines code page support for international systems.

### Format:

```
codepage_number = xlat_table, OEMfont, WOAfont, "description"
```

## Field Definitions:

Field	Description
----	-----
codepage_number	Table number for keyboard character mapping
xlat_table	Translation table filename for OEM font association
OEMfont	OEM font filename with disk number
WOAfont	Windows grabber font filename with disk number
description	Country description in quotes

## Complete Standard Entries:

```
[codepages]
863= 1:xlat863.bin, 2:vga863.fon, 2:app850.fon, "Canadian-French (863)"
861= 2:xlat861.bin, 2:vga861.fon, 2:app850.fon, "Icelandic (861)"
865= 2:xlat865.bin, 2:vga865.fon, 2:app850.fon, "Nordic (865)"
850= 2:xlat850.bin, 2:vga850.fon, 2:app850.fon, "Multi-Lingual (850)"
860= 3:xlat860.bin, 2:vga860.fon, 2:app850.fon, "Portuguese (860)"
437= , , 2:dosapp.fon, "English (437)"
```

## Mouse Driver Sections

### [pointing.device] Section

Table of information for supported pointing devices.

#### Format:

```
keyname = mouse_driver, mouse_descriptor, VMD, optional_section
```

## Field Definitions:

Field	Description
----	-----
keyname	Profile name
mouse_driver	Mouse driver filename with disk number
mouse_descriptor	Driver description in quotes for Setup dialog
VMD	Virtual Mouse Device support filename with disk number
optional_section	Section with additional mouse driver information

## Special VMD Values:

- x:\*vmd
  - File built into WIN386.EXE (not separate file)

- x:

- Refers to disk where WIN386.EXE is located

### Complete Standard Entries:

```
[pointing.device]
hpmouse= 2:hpmouse.drv, "HP Mouse (HP-HIL)", x:*vmd
lmouse= 3:lmouse.drv, "Logitech", 2:lvmd.386, lmouse
ps2mouse= 2:mouse.drv, "Microsoft, or IBM PS/2", x:*vmd
genius1= 2:mscmouse.drv, "Genius serial mouse on COM1", 1:mscvmd.386
genius2= 2:msc3bc2.drv, "Genius serial mouse on COM2", 1:mscvmd.386
msmouse2= 2:mscmouse.drv, "Mouse Systems serial or bus mouse", 1:mscvmd.386
msmouse1= 2:msc3bc2.drv, "Mouse Systems serial mouse on COM2", 1:mscvmd.386
nomouse= 2:nomouse.drv, "No mouse or other pointing device", x:*vmd
kbdmouse= 2:kbdmouse.drv, "Olivetti/AT&T Keyboard Mouse", x:*vmd
```

### [dos.mouse.driver] Section

Maps Windows mouse drivers to MS-DOS mouse drivers.

### Complete Standard Entries:

```
[dos.mouse.drivers]
mouse.sys= 4:mouse.SYS, "MS DOS Mouse driver .SYS ver 7.XX"
mouse.com= 4:mouse.com, "MS DOS Mouse driver .COM ver 7.XX"
mousehp.sys= 3:mousehp.SYS, "HP DOS Mouse driver .SYS ver 7.XX"
mousehp.com= 3:mousehp.com, "HP DOS Mouse driver .COM ver 7.XX"
```

### [lmouse] Section

Support data for Logitech MS-DOS mouse driver.

### Complete Standard Entry:

```
[lmouse]
2:lmouse.com,0:,,,
```

## Network Installation Sections

### [network] Section

Associates network keynames with installation files.

### Format:

network\_keyname = driver, description, HelpFile, optional\_file, WininiSectName, SysiniSectName, VDD, ...

### Field Definitions:

Field	Description
-----	-----
network_keyname	Profile for specific network driver
driver	Network driver filename with disk number
description	Driver description in quotes for Setup dialog
HelpFile	Associated help filename
optional_file	Optional file to install
WininiSectName	WIN.INI section to add/modify
SysiniSectName	SYSTEM.INI section to add/modify
VDD	Virtual Display Device support filenames

### Complete Standard Entries:

```
[network]
nonet= ,"No Network Installed"
3open= ,"3Com 3+Open"
3share= ,"3Com 3+Share" ,.,msnet_stuff
lantastic= ,"Artisoft LANtastic"
banyan= ,"Banyan Vines"
dlr= ,"IBM OS/2 LAN Server"
pclp= ,"IBM PC LAN Program"
lanman= ,"Microsoft LAN Manager"
msnet= ,"Microsoft Network (or 100% compatible)", .,msnet_stuff
novell= ,"Novell Netware"
pathworks= ,"DEC Pathworks"
10net= ,"TCS 10Net"
```

### [Network\_Version] Sections

Provide version-specific network information.

### Available Version Sections:

```
[10net.versions] ; TCS 10Net
[3open.versions] ; 3Com 3+Open
[banyan.versions] ; Banyan Vines
[dlr.versions] ; IBM OS/2 LAN Server
[lanman.versions] ; Microsoft LAN Manager
[lantastic.versions] ; Artisoft LANtastic
[novell.versions] ; Novell Netware
[pathworks.versions] ; DEC Pathworks
```

```
[pclp.versions] ; IBM PC LAN Program
```

**Format:**

```
version_number = "description", optional_files, optional_sections
```

**Example for LAN Manager:**

```
[lanman.versions]
xx000000="versions 1.X", , lmbasic
00020000="version 2.00 Basic", , lmbasic
01020000="version 2.00 Enhanced", , lmenh20
00021000="version 2.10 Basic", , lmbasic21
01021000="version 2.10 Enhanced", lanman21.driv, lmenh21 nodrv,lmenh21
```

**[Network\_Specific] Sections**

Define INI file modifications for specific networks.

**Available Network\_Specific Sections:**

```
[10net41], [10net41a], [10net42], [10net42def], [10net50]
[3open1]
[ban4], [ban41], [ban41def]
[dec4], [dec41]
[dlr12], [dlr12csd], [dlr13]
[lant1], [lant4], [lant4def]
[lmbasic], [lmbasic21], [lmenh20], [lmenh21], [lmenh21nodrv]
[msnet_stuff]
[novell301], [novell321]
[old_pclp], [pclp132]
[unsupported_net]
```

**Format:**

```
[network_keyname]
ini-keyname = section, entry_keyname, value
```

**Example for Novell NetWare 3.01:**

```
[novell301]
warning=2
driver=2:netware.driv
vxd=x:*vnetbios,2:vnetware.386,2:vipx.386
sysdir=2:netware.hlp,2:nwpopup.exe
windir=2:ipx.obj,2:ipxodi.com,2:netx.com,2:lsl.com
windir=2:tbmi2.com
```

## System Fonts Sections

### [sysfonts] Section

System fonts by display resolution.

#### Complete Standard Entries:

```
[sysfonts]
1:egasys.fon,"EGA (640x350) resolution System Font", "133,96,72"
1:vgasys.fon,"VGA (640x480) resolution System Font", "100,96,96"
1:8514sys.fon,"8514/a (1024x768) resolution System Font", "100,120,120"
1:egasys.fon,"AT&T (640x400) resolution System Font", "120,96,80"
```

### [fixedfonts] Section

Fixed-width system fonts by display resolution.

#### Complete Standard Entries:

```
[fixedfonts]
2:egafix.fon,"EGA (640x350) resolution Fixed System Font", "133,96,72"
1:vgafix.fon,"VGA (640x480) resolution Fixed System Font", "100,96,96"
1:8514fix.fon,"8514/a (1024x768) resolution Fixed System Font",
"100,120,120"
2:egafix.fon,"AT&T (640x400) resolution Fixed System Font", "120,96,80"
```

### [oemfonts] Section

Terminal fonts by display resolution.

#### Complete Standard Entries:

```
[oemfonts]
1:egaoem.fon,"EGA (640x350) resolution Terminal Font (USA/Europe)",
"133,96,72",1
1:vgaoem.fon,"VGA (640x480) resolution Terminal Font (USA/Europe)",
"100,96,96",1
1:8514oem.fon,"8514/a (1024x768) resolution Terminal Font (USA/Europe)",
"100,120,120",1
1:egaoem.fon,"AT&T (640x400) resolution Terminal Font
(USA/Europe)", "120,96,80",1
```

## Program Manager Groups Sections

### [new.groups] Section

Used when upgrading from Windows 3.0 to 3.1.

#### Format:

```
section = Progman_group, Min/Max
```

#### Field Definitions:

Field	Description
----	-----
section	Name of [group#] section with group definition
Progman_group	Profile name identifying group in Program Manager
Min/Max	1=maximize group, nothing=minimize group

#### Complete Standard Entries:

```
[new.groups]
group7=Main, 1
group1=Startup
group2=Accessories
group6=Games
```

### [progman.groups] Section

Used for new Windows 3.1 installations.

#### Complete Standard Entries:

```
[progman.groups]
group3=Main, 1
group4=Accessories
group5=Games
group1=Startup
```

### [group#] Sections

Define program items within Program Manager groups.

#### Format:

```
"description", filename.exe, icon_filename, icon_number, profile
```

#### Field Definitions:

Field	Description
-----	-----
description	Text below icon in Program Manager (in quotes)
filename.exe	Executable filename with extension
icon_filename	Icon extraction file (blank = first icon from filename.exe)
icon_number	Icon offset number (for 3rd icon, specify 2)
profile	If null, always added; otherwise only if installed via Add/Remove Files

### Complete Group Definitions:

#### Main Group ([group3] for [progman.groups]):

```
[group3]
"File Manager", WINFILE.EXE
"Control Panel", CONTROL.EXE
"Print Manager", PRINTMAN.EXE
"Clipboard Viewer", CLIPBRD.EXE
"MS-DOS Prompt", DOSPRMPT.PIF, PROGMAN.EXE, 9
"Windows Setup", SETUP.EXE
"PIF Editor", PIFEDIT.EXE
"Read Me", README.WRI,, readme
```

#### Accessories Group ([group4] for [progman.groups]):

```
[group4]
"Write", WRITE.EXE,,, write
"Paintbrush", PBRUSH.EXE,,, pbrush
"Terminal", TERMINAL.EXE,,, terminal
"Notepad", NOTEPAD.EXE,,, notepad
"Recorder", RECORDER.EXE,,, recorder
"Cardfile", CARDFILE.EXE,,, cardfile
"Calendar", CALENDAR.EXE,,, calendar
"Calculator", CALC.EXE,,, calc
"Clock", CLOCK.EXE,,, clock
"Object Packager", PACKAGER.EXE,,, packager
"Character Map", CHARMAP.EXE,,, charmap
"Media Player", MPLAYER.EXE,,, mplayer
"Sound Recorder", SOUNDREC.EXE,,, soundrec
```

#### Games Group ([group5] for [progman.groups]):

```
[group5]
"Solitaire", SOL.EXE,,, sol
"Minesweeper", WINMINE.EXE,,, winmine
```

#### Additional Groups for [new.groups]:

```
[group1] ; For [progman.groups] and [new.groups]
```



```
[group2] ; For [new.groups]
"Object Packager", PACKAGER.EXE,,, packager
"Character Map", CHARMAP.EXE,,, charmap
"Media Player", MPLAYER.EXE,,, mplayer
"Sound Recorder", SOUNDREC.EXE,,, soundrec
"PIF Editor"
"Write", WRITE.EXE
"Control Panel"

[group6] ; For [new.groups]
"Solitaire", SOL.EXE,,, sol
"Minesweeper", WINMINE.EXE,,, winmine

[group7] ; For [new.groups]
"PIF Editor", PIFEDIT.EXE
"Read Me"
"Read Me", README.WRI,, readme
"Tutorial"
```

## Fonts Sections

### [fonts] Section

Raster and vector screen fonts based on display resolution.

#### Format:

```
filename, "description", "resolution"
```

#### Example VGA Entries:

```
[fonts]
(other entries)
6:SSERIFE.FON, "MS Sans Serif 8,10,12,14,18,24 (VGA res)", "100,96,96"
(other entries)
6:COURE.FON, "Courier 10,12,15 (VGA res)", "100,96,96"
(other entries)
6:SERIFE.FON, "MS Serif 8,10,12,14,18,24 (VGA res)", "100,96,96"
(other entries)
6:SYMBOLE.FON, "Symbol 8,10,12,14,18,24 (VGA res)", "100,96,96"
(other entries)
6:SMALLE.FON, "Small (VGA res)", "100,96,96"
```

### [tffonts] Section

TrueType font definitions.

#### Format:

font\_header\_file, "description", font\_file, fontfamily\_flags

### Field Definitions:

Field	Description
----	-----
font_header_file	TrueType header source filename
description	Font description in quotes (first letter of each word capitalized)
font_file	TrueType font filename
fontfamily_flags	Font family name plus flag in quotes

### Font Family Flags:

- 0000 = Normal weight font
- 0100 = Bold font
- 1000 = Italic font
- 1100 = Bold Italic font

### Complete TrueType Entries:

```
[ttfonts]
S:ARIAL.FOT, "Arial (TrueType)", 5:arial.ttf, ""
S:ARIALBD.FOT, "Arial Bold (TrueType)", S:arialbd.ttf, "Arial0100"
S:ARIALBI.FOT, "Arial Bold Italic (TrueType)", 5:arialbi.ttf, "Arial1100"
S:ARIALI.FOT, "Arial Italic (TrueType)", 5:ariali.ttf, "Arial1000"
S:COUR.FOT, "Courier New (True Type)", 5:cour.ttf, ""
S:COURBD.FOT, "Courier New Bold (TrueType)", 5:courbd.ttf, "Courier0100"
S:COURBI.FOT, "Courier New Bold Italic (TrueType)", 5:courbi.ttf,
"Courier1100"
S:COURI.FOT, "Courier New Italic (TrueType)", 5:couri.ttf, "Courier1000"
3:TIMES.FOT, "Times New Roman (TrueType)", 4:times.ttf, ""
3:TIMESBD.FOT, "Times New Roman Bold (TrueType)", 4:timesbd.ttf, "Times New
Roman0100"
3:TIMESBI.FOT, "Times New Roman Bold Italic (TrueType)", 4:timesbi.ttf,
"Times New Roman1100"
4:TIMESI.FOT, "Times New Roman Italic (TrueType)", 4:timesi.ttf, "Times New
Roman1000"
S:SYMBOL.FOT, "Symbol (TrueType)", S:symbol.ttf, ""
```

## Incompatible Driver Sections

Four sections for checking incompatible drivers and TSRs:

### [compatibility] Section

Files listed here have their CONFIG.SYS commands removed during Setup.

## **[incompTSR1] Section**

TSRs and drivers that prevent Setup from running. Must be removed from memory and AUTOEXEC.BAT/CONFIG.SYS before running Setup.

## **[incompTSR2] Section**

TSRs and drivers that cause problems during Setup or when starting Windows.

## **[block\_devices] Section**

Block devices that are not compatible with Windows 3.1.

## **Miscellaneous Sections**

### **[installable.drivers] Section**

Multimedia driver specifications.

#### **Format:**

```
keyname= filename, types, description, VxDs, default_parameters
```

#### **Complete Standard Entries:**

```
[installable.drivers]
adlib= 3:adlib.drv,"MIDI","Ad Lib",4:vadlibd.386,
lapcl= 3:mpu401.drv,"MIDI","Roland LAPC1",,
midimapper= 4:midimap.drv,"MidiMapper","MIDI Mapper",,
mpu401= 3:mpu401.drv,"MIDI","Roland MPU401",,
sequencer= 4:mciseq.drv,"Sequencer","[MCI] MIDI Sequencer",,
soundblaster= 3:sndblst.drv,"Wave,MIDI","Creative Labs Sound Blaster
1.0",3:vsbd.386,,adlib
soundblaster2= 3:sndblst2.drv,"Wave,MIDI","Creative Labs Sound Blaster
1.5",3:vsbd.386,,adlib
timer= 5:timer.drv,"Timer","Timer",5:vtdapi.386,
thunder= 3:sndblst2.drv,"Wave,MIDI","Media Vision Thunder
Board",3:vsbd.386,,adlib
wave= 4:mcwave.drv,"WaveAudio","[MCI] Sound",,, "4"
```

## **[translate] Section**

OEM filename translations.

## Example Entries:

```
[translate]
WinDiskName=25,"Microsoft Windows 3.0 Disk"
WinDiskName=14,"Windows Disk#"
*vddvga=2:vddvga30.386
ctil.lgo=2:herclogo.lgo
herclogo.rle=1:herclogo.rle
vddega=2:vddega.386
vgacolor.gr2=3:vgacolor.2gr
vgalogo.lgo=2:vgalogo.lgo
vgalogo.rle=2:vgalogo.rle
rgdi.lgo=2:vgalogo.lgo
rgdi.rle=2:vgalogo.rle
vga.gr3=1:vga30.3gr
```

## [update.files] Section

Installable drivers to update if earlier versions are found.

### Format:

```
location, filename
```

### Location Values:

- 0: = WINDOWS directory
- 0:system = SYSTEM subdirectory

## Complete Standard Entries:

```
[update.files]
0:system,3:sndblst.drv
0:system,3:sndblst2.drv
0:system,3:adlib.drv
0:system,3:mpu401.drv
0:system,5:vtdapi.386
0:system,3:vsbd.386
0:system,4:vadlibd.386
```

## [Update.Dependents] Section

Updates files dependent on those listed in [Update.Files].

## Complete Standard Entries:

```
[Update.Dependents]
```

```
msadlib.drv = 4:vadlibd.386
sndblst.drv = 4:vsbd.386
sndblst2.drv = 4:vsbd.386
```

### [ini.upd.patches] Section

Temporary INI file profile renaming during Setup.

#### Format:

```
ini_file, section, temporary_profile, original_profile
```

#### Example Entries:

```
[ini.upd.patches]
system.ini, Boot, "olddrivers","drivers"
win.ini, Desktop, "oldwallpaper","wallpaper"
system.ini, Boot, "oldtaskman","taskman.exe"
```

### [blowaway] Section

Marks the end of installation information and start of configuration sections. Windows Mode Setup stops reading SETUP.INF here.

### [ini.upd.31] Section

INI file updates for Windows 3.0 to 3.1 upgrade.

#### Format:

```
ini_file, section, OldEntry, NewEntry
```

#### Example Entries:

```
[ini.upd.31]
system.ini, 386Enh, "keyboard=*vkd"
system.ini, 386Enh, "device=*vpicd"
system.ini, 386Enh, "device=*blockdev"
system.ini, 386Enh, , "device=*pagefile"
win.ini, FontSubstitutes, , "Helv=MS Sans Serif"
win.ini, FontSubstitutes, , "Tms Rmn=MS Serif"
win.ini, FontSubstitutes, , "Courier=Courier New"
win.ini, FontSubstitutes, , "Times=Times New Roman"
win.ini, FontSubstitutes, , "Helvetica=Arial"
```

## System Configuration Sections

### [system] Section

Maps system short names to appropriate system files.

#### Complete Standard Entries:

```
[system]
system= 2:system.drv
sound= 1:mmsound.drv
comm= 1:comm.drv
hpsystem= 2:hpsystem.drv
```

### [machine] Section

Installs appropriate system files for various machines.

#### Format:

```
keyname= description, system_drv, kbd_drv, kbd_type, mouse_drv, disp_drv,
sound_drv, comm_drv, himem_switch, ebios, Cookz
```

#### Complete Field Definitions:

Field	Description
-----	-----
keyname	Profile string for the system
description	System description in quotes for Setup dialog
system_drv	Short name for system driver from [system]
kbd_drv	Short name for keyboard driver from [keyboard.drivers]
kbd_type	Short name for keyboard type from [keyboard.types]
mouse_drv	Mouse driver keyname from [pointing.device]
disp_drv	Display driver keyname from [display]
sound_drv	Sound driver name from [system]
comm_drv	Communications driver name from [system]
himem_switch	A20 handler number (1-8) for HIMEM.SYS extended memory access
ebios	EBIOS support defined in [ebios]
Cookz	[Cookz] section with INI file modification information

**Important:** Do not change the order of entries in [machine] section.

#### Example Entries:

```
[machine]
```

```
ibm_compatible= "MS-DOS
System",system,kbd,t4s0enha,nomouse,egahires,sound,comm,,ebios,
ast_386_486= "AST: all 80386 and 80486 based
machines",system,kbd,t4s0enha,nomouse,egahires,sound,comm,,ebios,ast_cookz
at_and_t= "AT&T PC",system,kbd,t4s0enha,nomouse,vgahires,sound,comm,,ebios,
```

## [Cookz] Sections

Hardware-specific INI file modifications.

### Available Cookz Sections:

```
[apm_cookz], [apm_sl_cookz], [ast_cookz], [everex_cookz], [ibm140_cookz],
[ncr386sx_cookz], [nec_pm_cookz], [t5200_cookz], [zen386_cookz]
```

### Format:

```
ini_file, section, cookie, needed_file
```

### Example Entries:

```
[ast_cookz]
system.ini,386enh,"emmexclude=E000-EFFF",

[apm_cookz]
specialdriver,,,5:power.drv
system.ini,386enh, "device=vpowerd.386",5:vpowerd.386
,,,5:power.hlp
```

## [special\_adapter] Section

Support for special adapters requiring additional files.

### Complete Standard Entries:

```
[special_adapter]
etherlink= DMAbuffersize,32 ; Needed if EtherLink MC is detected
cdrom= 2:lanman10.386 ; Needed for CD ROM extensions
```

## [ebios] Section

Extended BIOS support files.

### Complete Standard Entries:

```
[ebios]
ebios= x:*ebios ; Required for most 386 machines
```

```
hpebios= 2:hpebios.386,x:*ebios ; Required for HP 386 machines
```

## [language] Section

Language support libraries.

### Format:

```
keyname= language_DLL, DLL_description, language_ID
```

### Complete Standard Entries:

```
[language]
dan= 2:langsca.dll, "Danish", 1030
nld= 2:langdut.dll, "Dutch", 1043
enu=, "English (American)", 1033
eng= 2:langeng.dll, "English (International)", 2057
fin= 2:langsca.dll, "Finnish", 1035
fra= 2:langfrn.dll, "French", 1036
frc= 2:langeng.dll, "French Canadian", 3084
deu= 2:langger.dll, "German", 1031
isl= 2:langsca.dll, "Icelandic", 1039
ita= 2:langeng.dll, "Italian", 1040
nor= 2:langsca.dll, "Norwegian", 1044
ptg= 2:langeng.dll, "Portuguese", 2070
esp= 2:langspa.dll, "Spanish (Classic)", 1034
esn= 2:langeng.dll, "Spanish (Modern)", 3082
sve= 2:langsca.dll, "Swedish", 1053
```

## File Copying Mechanism Details

The SETUP.INF file copying system operates through these key mechanisms:

### 1. Destination Directories Definition:

```
[DestinationDirs]
DefaultDestDir    = 25, ""           ; Windows directory (e.g.,
C:\WINDOWS)
system             = 25, "system"     ; SYSTEM subdirectory
winabc            = 25, "winabc"      ; WINABC subdirectory
root              = 10, ""           ; Root directory (e.g., C:\)
```

### Directory ID Codes:

- 25 - Windows directory
- 10 - Root directory of boot drive
- 11 - System directory



- 30 - Root directory of installation drive A:

## 2. Disk Number References: File references like

```
2:filename.ext
```

refer to disk numbers defined in [disks] section.

## 3. File Selection Process:

1. Setup reads hardware configuration
2. Matches configuration to [machine] section entries
3. Resolves short names to actual files through related sections
4. Copies files to destinations specified in [DestinationDirs]
5. Updates dependencies through [Update.Dependents]

## 4. Example Resolution Chain:

```
[machine] entry: ast_386_486= ... ,system, ...  
[system] section: system= 2:system.drv  
[disks] section: 2=. , "Microsoft Windows 3.1 Disk #2", disk2  
Result: Copies system.drv from Disk #2 to appropriate directory
```

This comprehensive SETUP.INF reference provides complete documentation of all installation parameters and processes for Windows 3.1, ensuring accurate system configuration and software installation across all supported hardware platforms.

From:

<https://cocorico.osfree.org/doku/> - osFree wiki

Permanent link:

<https://cocorico.osfree.org/doku/doku.php?id=en:docs:win16:applications:setup&rev=1761026480>

Last update: **2025/10/21 06:01**

