



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

DosGetCollate

This call obtains a collating sequence table (for characters hex 00H through FFH) that resides in the country information file. It is used by the [SORT](#) utility to sort text according to the collating sequence.

Syntax

```
DosGetCollate (Length, Country, MemoryBuffer, DataLength)
```

Parameters

- Length ([USHORT](#)) - input: Length, in bytes, of the data area (MemoryBuffer). A length value of 256 is sufficient.
- Country ([PCOUNTRYCODE](#)) - input: Address of the country information structure
- MemoryBuffer ([PCHAR](#)) - output: Address of the collating table. This memory area is provided by the caller. The size of the area is provided by the input parameter Length. If it is too small to hold all the available information then as much information as possible is provided in the available space (in the order that the data would appear). If the amount of returned data does not fill the memory area provided by the caller, the unaltered memory is set at 0.

The buffer format for the returned information is:

Byte	Description
0	Sort weight of ASCII (0)
1	Sort weight of ASCII (1)
.	
.	
.	
255	Sort weight of ASCII (255)

- DataLength ([PUSHORT](#)) - output : Address of the length, in bytes, of the collate table.

Returns

rc ([USHORT](#)) - return:Return code descriptions are:

- 0 NO_ERROR
- 396 ERROR_NLS_NO_COUNTRY_FILE
- 397 ERROR_NLS_OPEN_FAILED
- 398 ERROR_NO_COUNTRY_OR_CODEPAGE
- 399 ERROR_NLS_TABLE_TRUNCATED

Remarks

The returned country-dependent information can be for the default country and current process code page or for a specific country and code page. For more information see [DosSetCp](#).

Bindings

C

```
typedef struct _COUNTRYCODE {    /* ctryc */

    USHORT country;              /* country code */
    USHORT codepage;            /* code page */

} COUNTRYCODE;

#define INCL_DOSNLS

USHORT rc = DosGetCollate(Length, Structure, MemoryBuffer, DataLength);

USHORT      Length;            /* Length of data area provided */
PCOUNTRYCODE Structure;        /* Input data structure */
PCHAR       MemoryBuffer;      /* Collate table (returned) */
PUSHORT     DataLength;        /* Length of collate table (returned) */

USHORT      rc;                /* return code */
```

MASM

```
COUNTRYCODE struc
    ctryc_country    dw    ? ;country code
    ctryc_codepage   dw    ? ;code page
COUNTRYCODE ends

EXTRN  DosGetCollate:FAR
INCL_DOSNLS      EQU 1
```

PUSH

WORD

Length

;Length of data area provided

PUSH@

OTHER

Structure

;Input data structure

PUSH@

OTHER

MemoryBuffer

;Collate table (returned)

PUSH@

WORD

DataLength

;Length of collate table (returned)

CALL

DosGetCollate

Returns WORD

Example

This example gets a collating sequence table for codepage 850 and the current country.

```
#define INCL_DOSNLS
#define CURRENT_COUNTRY 0
#define NLS_CODEPAGE 850

COUNTRYCODE Country;
CHAR CollBuffer[256];
USHORT Length;
USHORT rc;

Country.country = CURRENT_COUNTRY;
Country.codepage = NLS_CODEPAGE;

rc = DosGetCollate(sizeof(CollBuffer), /* Length of data area provided */
                  &Country,           /* Input data structure */
                  CollBuffer,          /* Data area to contain collate
table */
                  &Length);           /* Length of table */
```

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOctl DosDevIOctl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec

Family API

KBD	KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools	BIND
Modules	DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · [prokushev](#) · [0 Comments](#)

From:

<http://cocorico.osfree.org/doku/> - **osFree wiki**

Permanent link:

<http://cocorico.osfree.org/doku/doku.php?id=en:docs:fapi:dosgetcollate&rev=1631963194>

Last update: **2021/09/18 11:06**

