

(Table 01356) Values for media ID byte: FFh floppy, double-sided, 8 sectors per track (320K) FEh floppy, single-sided, 8 sectors per track (160K) FDh floppy, double-sided, 9 sectors per track (360K) FCh floppy, single-sided, 9 sectors per track (180K) FAh HP 200LX D: ROM disk, 16 sectors per track (995K)

HP 200LX E: (Stacker host drive ???)

F9h floppy, double-sided, 15 sectors per track (1.2M)

floppy, double-sided, 9 sectors per track (720K,3.5")

F8h hard disk F0h other media

(e.g. floppy, double-sized, 18 sectors per track -- 1.44M,3.5")



**Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.**

2018/09/07 05:04 · prokushev · [0 Comments](#)

# Int 21H, AH=1BH

## Version

1 and higher

## Brief

GET ALLOCATION INFORMATION FOR DEFAULT DRIVE

## Family API

none

## Input

AH = 1Bh

## Return

AL = sectors per cluster (allocation unit)

```
CX = bytes per sector
DX = total number of clusters
DS:BX -> media ID byte (see #01356)
```

## Notes

under DOS 1.x, DS:BX points at an actual copy of the FAT; later

```
versions return a pointer to a copy of the FAT's ID byte
this function may not be properly supported on CD-ROMs and other
installable file systems (use AX=4402h"CD-ROM" for CD-ROMs
instead)
```

BUG: DOS 7.10 (Win95B/Win98) reportedly returns incorrect values in AL and

```
DX for FAT12/FAT16 drives, even though it manages correct results
for FAT32 drives (DOS windows are not affected, only real-mode
DOS)
```

## See also

AH=1Ch,AH=36h

## Note

Text based on [Ralf Brown Interrupt List Release 61](#)

| DOS API              |                                                                                                                                                                                                                                                                                                                                                            |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Process manager      | INT 20H, <b>INT 21H</b> : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H                                                                                                                                                                                                                                  |
| File manager         | INT 25H, INT 26H, <b>INT 21H</b> : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH |
| Character Device I/O | INT 29H, <b>INT 21H</b> : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH                                                                                                                                                                                                                                      |
| Signals              | INT 23H, INT 24H, <b>INT 21H</b> : 3300H, 3301H, 3302H                                                                                                                                                                                                                                                                                                     |

| <b>DOS API</b> |                                                                                                                                                                                        |
|----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Memory manager | <b>INT 21H:</b> 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H                                                                                                                              |
| Date and Time  | <b>INT 21H:</b> 2AH, 2BH, 2CH, 2DH                                                                                                                                                     |
| Misc           | <b>INT 21H:</b> 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H                                                                                                                            |
| NLS            | <b>INT 21H:</b> 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H |
| Devices        | <b>INT 21H:</b> 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H                                      |
| Network        | <b>INT 21H:</b> 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H                                                                       |

### osFree Macro Library

|                |                                                                                                                                                                                                                    |
|----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Video I/O      | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls |
| Hardware info  | @Equipment @MemSize                                                                                                                                                                                                |
| Serial I/O     | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus                                                                                                                                                                   |
| Tape I/O       | @TapeOn @TapeOff @TapeRead @TapeWrite                                                                                                                                                                              |
| Keyboard I/O   | @KbdStatus @CharIn @CharPeek                                                                                                                                                                                       |
| Printer I/O    | @PrnPrint @PrnInit @PrnStatus                                                                                                                                                                                      |
| Disk I/O       | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat                                                                                                                                                      |
| Date and Time  | @SetTime @GetTime                                                                                                                                                                                                  |
| Mouse          | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion                                                                                                                                            |
| Memory manager | @ModBlok SET_BLOCK                                                                                                                                                                                                 |

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

| Family API |                                                                        |                                                                                                                                                                                                                                                                                                                                                                              |
|------------|------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DOS        | Process Manager                                                        | DosBeep DosExit DosSleep DosExecPgm                                                                                                                                                                                                                                                                                                                                          |
|            | File Manager                                                           | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSInfo DosShutdown |
|            | Memory Manager                                                         | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias                                                                                                                                                                                                                                           |
|            | NLS                                                                    | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage                                                                                                                                                                                                                                                                |
|            | Date and Time                                                          | DosSetDateTime DosGetDateTime                                                                                                                                                                                                                                                                                                                                                |
|            | Devices                                                                | DosDevConfig DosDevIOctl DosDevIOctl2                                                                                                                                                                                                                                                                                                                                        |
|            | Signals                                                                | DosHoldSignal DosSetSigHandler                                                                                                                                                                                                                                                                                                                                               |
|            | Misc                                                                   | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec                                                                                                                                                                                                                                                                                          |
| KBD        | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek |                                                                                                                                                                                                                                                                                                                                                                              |

| Family API |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| VIO        | <a href="#">VioGetBuf</a> <a href="#">VioGetConfig</a> <a href="#">VioGetCurPos</a> <a href="#">VioGetCurType</a> <a href="#">VioGetPhysBuf</a><br><a href="#">VioReadCellStr</a> <a href="#">VioReadCharStr</a> <a href="#">VioScrollUp</a> <a href="#">VioScrollDn</a> <a href="#">VioScrollLf</a> <a href="#">VioScrollRt</a><br><a href="#">VioScrUnLock</a> <a href="#">VioSetCurPos</a> <a href="#">VioSetCurType</a> <a href="#">VioSetMode</a> <a href="#">VioGetMode</a> <a href="#">VioShowBuf</a><br><a href="#">VioWrtCellStr</a> <a href="#">VioWrtCharStr</a> <a href="#">VioWrtCharStrAtt</a> <a href="#">VioWrtNAttr</a> <a href="#">VioWrtNCell</a><br><a href="#">VioWrtNChar</a> <a href="#">VioWrtTTY</a> <a href="#">VioScrLock</a> <a href="#">VioPopUp</a> |
| Tools      | <a href="#">BIND</a>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Modules    | <a href="#">DOSCALLS.DLL</a> <a href="#">VIOCALLS.DLL</a> <a href="#">KBDCALLS.DLL</a> <a href="#">MSG.DLL</a>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| Libraries  | <a href="#">API.LIB</a> <a href="#">OS2386.LIB</a> <a href="#">FAPI.LIB</a> <a href="#">DOSCALLS.LIB</a> <a href="#">SUBCALLS.LIB</a>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |

2018/08/25 15:05 · [prokushev](#) · [0 Comments](#)

From:  
<https://cocorico.osfree.org/doku/> - **osFree wiki**

Permanent link:  
<https://cocorico.osfree.org/doku/doku.php?id=en:docs:dos:api:int21:1b&rev=1607417020>

Last update: **2020/12/08 08:43**

