



**Note:** This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

# Int 21H, AH=21H

## Version

1 and higher

## Brief

READ RANDOM RECORD FROM FCB FILE

## Family API

## Input

AH = 21h  
DS:DX -> opened FCB (see #01345)

## Return

AL = status

00h successful  
01h end of file, no data read  
02h segment wrap in DTA, no data read  
03h end of file, partial record read  
Disk Transfer Area filled with record read from file

## Notes

the record is read from the current file position as specified by the  
random record and record size fields of the FCB  
the file position is not updated after reading the record

if a partial record is read, it is zero-padded to the full size  
not supported by MS Windows 3.0 DOSX.EXE DOS extender

## See also

AH=14h,AH=22h,AH=27h,AH=3Fh“DOS”

## Note

Text based on [Ralf Brown Interrupt List Release 61](#)

| DOS API              |                                                                                                                                                                                                                                                                                                                                                            |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Process manager      | INT 20H, <b>INT 21H</b> : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H                                                                                                                                                                                                                                  |
| File manager         | INT 25H, INT 26H, <b>INT 21H</b> : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH |
| Character Device I/O | INT 29H, <b>INT 21H</b> : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH                                                                                                                                                                                                                                      |
| Signals              | INT 23H, INT 24H, <b>INT 21H</b> : 3300H, 3301H, 3302H                                                                                                                                                                                                                                                                                                     |
| Memory manager       | <b>INT 21H</b> : 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H                                                                                                                                                                                                                                                                                                 |
| Date and Time        | <b>INT 21H</b> : 2AH, 2BH, 2CH, 2DH                                                                                                                                                                                                                                                                                                                        |
| Misc                 | <b>INT 21H</b> : 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H                                                                                                                                                                                                                                                                                               |
| NLS                  | <b>INT 21H</b> : 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H                                                                                                                                                                    |
| Devices              | <b>INT 21H</b> : 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H                                                                                                                                                                                                         |
| Network              | <b>INT 21H</b> : 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H                                                                                                                                                                                                                                          |
| osFree Macro Library |                                                                                                                                                                                                                                                                                                                                                            |
| Video I/O            | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @CIs                                                                                                                                         |
| Hardware info        | @Equipment @MemSize                                                                                                                                                                                                                                                                                                                                        |
| Serial I/O           | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus                                                                                                                                                                                                                                                                                                           |
| Tape I/O             | @TapeOn @TapeOff @TapeRead @TapeWrite                                                                                                                                                                                                                                                                                                                      |
| Keyboard I/O         | @KbdStatus @CharIn @CharPeek                                                                                                                                                                                                                                                                                                                               |
| Printer I/O          | @PrnPrint @PrnInit @PrnStatus                                                                                                                                                                                                                                                                                                                              |
| Disk I/O             | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat                                                                                                                                                                                                                                                                                              |
| Date and Time        | @SetTime @GetTime                                                                                                                                                                                                                                                                                                                                          |

**osFree Macro Library**

|                |                                                                            |
|----------------|----------------------------------------------------------------------------|
| Mouse          | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey<br>@MouRegion |
| Memory manager | @ModBlok SET_BLOCK                                                         |

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

**Family API**

|           |                 |                                                                                                                                                                                                                                                                                                                                                                                             |
|-----------|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DOS       | Process Manager | DosBeep DosExit DosSleep DosExecPgm                                                                                                                                                                                                                                                                                                                                                         |
|           | File Manager    | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove<br>DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead<br>DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose<br>DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks<br>DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo<br>DosShutdown |
|           | Memory Manager  | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg<br>DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias                                                                                                                                                                                                                                                       |
|           | NLS             | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate<br>DosGetMessage DosInsMessage DosPutMessage                                                                                                                                                                                                                                                                            |
|           | Date and Time   | DosSetDateTime DosGetDateTime                                                                                                                                                                                                                                                                                                                                                               |
|           | Devices         | DosDevConfig DosDevIOCtl DosDevIOCtl2                                                                                                                                                                                                                                                                                                                                                       |
|           | Signals         | DosHoldSignal DosSetSigHandler                                                                                                                                                                                                                                                                                                                                                              |
|           | Misc            | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass<br>DosSetVec                                                                                                                                                                                                                                                                                                      |
| KBD       |                 | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek                                                                                                                                                                                                                                                                                                                      |
| VIO       |                 | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf<br>VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt<br>VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf<br>VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell<br>VioWrtNChar VioWrtTTY VioScrLock VioPopUp                                           |
| Tools     |                 | BIND                                                                                                                                                                                                                                                                                                                                                                                        |
| Modules   |                 | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL                                                                                                                                                                                                                                                                                                                                              |
| Libraries |                 | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB                                                                                                                                                                                                                                                                                                                                       |

2018/08/25 15:05 · prokushev · 0 Comments

From:

<https://cocorico.osfree.org/doku/> - **osFree wiki**

Permanent link:

<https://cocorico.osfree.org/doku/doku.php?id=en:docs:dos:api:int21:21&rev=1607477775>Last update: **2020/12/09 01:36**