



DosSetVerify

This call sets the verify switch.

Syntax

```
DosSetVerify (VerifySetting)
```

Parameters

- VerifySetting (USHORT) - input : New state of Verify Mode for the requesting process as shown below:

Value	Definition
0	Verify mode is not active.
1	Verify mode is active.

Return Code

- rc (USHORT) - return

Return code descriptions are:

- 0 NO_ERROR
- 11 ERROR_INVALID_VERIFY_SWITCH

Remarks

When verify is active, OS/2 performs a verify operation each time it does a file write to assure proper data recording on the disk. Although disk recording errors are rare, this function has been provided for applications to verify the proper recording of critical data.

Example Code

C Binding

```
#define INCL_DOSFILEMGR

USHORT rc = DosSetVerify(VerifySetting);
```

```
USHORT      VerifySetting; /* New value of verify switch */

USHORT      rc;             /* return code */
```

MASM Binding

```
EXTRN  DosSetVerify:FAR
INCL_DOSFILEMGR      EQU 1

PUSH    WORD    VerifySetting ;New value of verify switch
CALL    DosSetVerify
```

Returns WORD

Note

Text based on [http://www.edm2.com/index.php/DosSetVerify_\(FAPI\)](http://www.edm2.com/index.php/DosSetVerify_(FAPI))

Family API

DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSInfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · [0 Comments](#)

From:

<http://cocorico.osfree.org/doku/> - **osFree wiki**

Permanent link:

<http://cocorico.osfree.org/doku/doku.php?id=en:docs:fapi:dossetverify&rev=1535822963>

Last update: **2018/09/01 17:29**

