



# VIOCALLS

This is forwarder DLL to [DOSCALLS.DLL](#) on latest OS/2 versions. No any real code here.

## Entry points

| Ordinal | Name                       | Desc                      | Status | FAPI | Version |
|---------|----------------------------|---------------------------|--------|------|---------|
| 1       | VioEndPopup                | Forwarder to DOSCALLS.770 | Done   |      |         |
| 2       | VioGetPhysBuf              | Forwarder to DOSCALLS.771 | Done   |      |         |
| 3       | <a href="#">VioGetAnsi</a> | Forwarder to DOSCALLS.772 | Done   |      |         |
| 4       | VioFree                    | Forwarder to DOSCALLS.773 | Done   |      |         |
| 5       | VioSetAnsi                 | Forwarder to DOSCALLS.774 | Done   |      |         |
| 6       | VioDeRegister              | Forwarder to DOSCALLS.775 | Done   |      |         |
| 7       | VioScrollUp                | Forwarder to DOSCALLS.776 | Done   |      |         |
| 8       | VioPrtSc                   | Forwarder to DOSCALLS.777 | Done   |      |         |
| 9       | VioGetCurPos               | Forwarder to DOSCALLS.778 | Done   |      |         |
| 10      | VioWrtCellStr              | Forwarder to DOSCALLS.779 | Done   |      |         |
| 11      | VioPopUp                   | Forwarder to DOSCALLS.780 | Done   |      |         |
| 12      | VioScrollRt                | Forwarder to DOSCALLS.781 | Done   |      |         |
| 13      | VioWrtCharStr              | Forwarder to DOSCALLS.782 | Done   |      |         |
| 14      | Avs_Prtsc                  | Forwarder to DOSCALLS.783 | Done   |      |         |
| 15      | VioSetCurPos               | Forwarder to DOSCALLS.784 | Done   |      |         |
| 16      | VioSrfUnblock              | Forwarder to DOSCALLS.785 | Done   |      |         |
| 17      | VioSrfBlock                | Forwarder to DOSCALLS.786 | Done   |      |         |
| 18      | VioScrUnlock               | Forwarder to DOSCALLS.787 | Done   |      |         |
| 19      | VioWrtTty                  | Forwarder to DOSCALLS.788 | Done   |      |         |
| 20      | VioSave                    | Forwarder to DOSCALLS.789 | Done   |      |         |
| 21      | VioGetMode                 | Forwarder to DOSCALLS.790 | Done   |      |         |
| 22      | VioSetMode                 | Forwarder to DOSCALLS.791 | Done   |      |         |
| 23      | VioScrLock                 | Forwarder to DOSCALLS.792 | Done   |      |         |
| 24      | VioReadCellStr             | Forwarder to DOSCALLS.793 | Done   |      |         |
| 25      | VioSavRedrawWait           | Forwarder to DOSCALLS.794 | Done   |      |         |
| 26      | VioWrtNAttr                | Forwarder to DOSCALLS.795 | Done   |      |         |
| 27      | VioGetCurType              | Forwarder to DOSCALLS.796 | Done   |      |         |
| 28      | VioSavRedrawUndo           | Forwarder to DOSCALLS.797 | Done   |      |         |
| 29      | VioGetFont                 | Forwarder to DOSCALLS.798 | Done   |      |         |
| 30      | VioReadCharStr             | Forwarder to DOSCALLS.799 | Done   |      |         |
| 31      | VioGetBuf                  | Forwarder to DOSCALLS.800 | Done   |      |         |
| 32      | VioSetCurType              | Forwarder to DOSCALLS.801 | Done   |      |         |
| 33      | VioSetFont                 | Forwarder to DOSCALLS.802 | Done   |      |         |
| 34      | VioHetInit                 | Forwarder to DOSCALLS.803 | Done   |      |         |
| 35      | VioModeUndo                | Forwarder to DOSCALLS.804 | Done   |      |         |
| 36      | VioSswSwitch               | Forwarder to DOSCALLS.805 | Done   |      |         |

| Ordinal | Name                 | Desc                      | Status | FAPI | Version |
|---------|----------------------|---------------------------|--------|------|---------|
| 37      | VioModeWait          | Forwarder to DOSCALLS.806 | Done   |      |         |
| 38      | Avs_PrtscToggle      | Forwarder to DOSCALLS.807 | Done   |      |         |
| 40      | VioGetCp             | Forwarder to DOSCALLS.808 | Done   |      |         |
| 41      | VioRestore           | Forwarder to DOSCALLS.809 | Done   |      |         |
| 42      | VioSetCp             | Forwarder to DOSCALLS.810 | Done   |      |         |
| 43      | VioShowBuf           | Forwarder to DOSCALLS.811 | Done   |      |         |
| 44      | VioScrollLf          | Forwarder to DOSCALLS.812 | Done   |      |         |
| 45      | VioRegister          | Forwarder to DOSCALLS.813 | Done   |      |         |
| 46      | VioGetConfig         | Forwarder to DOSCALLS.814 | Done   |      |         |
| 47      | VioScrollDn          | Forwarder to DOSCALLS.815 | Done   |      |         |
| 48      | VioWrtCharStrAtt     | Forwarder to DOSCALLS.816 | Done   |      |         |
| 49      | VioGetState          | Forwarder to DOSCALLS.817 | Done   |      |         |
| 50      | VioPrtScToggle       | Forwarder to DOSCALLS.818 | Done   |      |         |
| 51      | VioSetState          | Forwarder to DOSCALLS.819 | Done   |      |         |
| 52      | VioWrtNCell          | Forwarder to DOSCALLS.820 | Done   |      |         |
| 53      | VioWrtNChar          | Forwarder to DOSCALLS.821 | Done   |      |         |
| 54      | VioShellInit         | Forwarder to DOSCALLS.822 | Done   |      |         |
| 55      | VioAssociate         | Forwarder to DOSCALLS.823 | Done   |      |         |
| 56      | VioCreatePS          | Forwarder to DOSCALLS.824 | Done   |      |         |
| 57      | VioDeleteSetId       | Forwarder to DOSCALLS.825 | Done   |      |         |
| 58      | VioGetDeviceCellSize | Forwarder to DOSCALLS.826 | Done   |      |         |
| 59      | VioGetOrg            | Forwarder to DOSCALLS.827 | Done   |      |         |
| 60      | VioCreateLogFont     | Forwarder to DOSCALLS.828 | Done   |      |         |
| 61      | VioDestroyPS         | Forwarder to DOSCALLS.829 | Done   |      |         |
| 62      | VioQuerySetIds       | Forwarder to DOSCALLS.830 | Done   |      |         |
| 63      | VioSetOrg            | Forwarder to DOSCALLS.831 | Done   |      |         |
| 64      | VioQueryFonts        | Forwarder to DOSCALLS.832 | Done   |      |         |
| 65      | VioSetDeviceCellSize | Forwarder to DOSCALLS.833 | Done   |      |         |
| 66      | VioShowPS            | Forwarder to DOSCALLS.834 | Done   |      |         |
| 67      | VioGetPSAddress      | Forwarder to DOSCALLS.835 | Done   |      |         |
| 68      | VioQueryConsole      | Forwarder to DOSCALLS.836 | Done   |      |         |
| 69      | VioRedrawSize        | Forwarder to DOSCALLS.837 | Done   |      |         |
| 70      | VioGlobalReg         | Forwarder to DOSCALLS.838 | Done   |      |         |
| 71      | XVioSetCAState       | Forwarder to DOSCALLS.839 | Done   |      |         |
| 72      | XVioCheckCharType    | Forwarder to DOSCALLS.840 | Done   |      |         |
| 73      | XVioDestroyCA        | Forwarder to DOSCALLS.841 | Done   |      |         |
| 74      | XVioCreateCA         | Forwarder to DOSCALLS.842 | Done   |      |         |
| 75      | VioCheckCharType     | Forwarder to DOSCALLS.843 | Done   |      |         |
| 76      | XVioGetCAState       | Forwarder to DOSCALLS.844 | Done   |      |         |


Violnit.39 is absent in latest OS/2 DLL


Versions

| Date&Time        | BldLevel/Version                                    | Size         | Comments         |
|------------------|-----------------------------------------------------|--------------|------------------|
| 2012-01-25 16:59 | 14.100                                              | 2,048 bytes  | osFree Video API |
| 2002-03-08 20:16 | N/A                                                 | 2,048 bytes  |                  |
| 1992-02-06 17:09 | IBM Personal Computer DOS Version 0.00 Video Router | 16,087       | IBM OS/2 SDK 1.3 |
| 1988-08-08 00:00 | IBM Personal Computer DOS Version 0.00 Video Router | 14,441 bytes | MS OS/2 SDK 1.05 |
| 1987-12-15 00:00 | Microsoft OS/2 Version 0.00 Video Router            | 13,981 bytes | MS OS/2 SDK 1.02 |
| 1987-10-21 00:00 | IBM Personal Computer DOS Version 0.00 Video Router | 13,981 bytes | MS SDK 1.0       |

OS/2 DLLs

|                                         |                                                                                                                                                |
|-----------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| Base API                                | DOSCALLS EMXWRAP SUB32 ANSICALL NLS MSG MONCALLS<br>KBDSCALLS MOUCALLS VIOCALLS SESMGR BKSCALLS BMSCALLS<br>BVSCALLS NAMPIPES QUECALLS OS2CHAR |
| Bidirectional NLS                       | BDCALLS BDCALLS32 BDIME BDBVH BDVIEW BDWPCLS BIDIPM<br>PMBIDI                                                                                  |
| Unicode API                             | UCONV UNIKBD LIBUNI                                                                                                                            |
| BVH (Base Video Handlers)               | BVHINIT BVHMPA BVHVGA BVHSVGA BVHWNDW                                                                                                          |
| GRADD subsystem                         | VMAN SOFTDRAW GRE2VMAN GENGRADD                                                                                                                |
| IPF (Information Presentation facility) | HELPMGR HPMGRMRI MINXOBJ IBMHMGR NEWVIEW MINXMRI<br>ERRTXT                                                                                     |
| REXX                                    | REXX REXXAPI REXXUTIL REGINA                                                                                                                   |
| The core PM DLL's                       | PMMERGE PMMRGRES PMSHAPI PMSHLTKT PMGRE PMGPI PMDRAG<br>PMCTLS PMMLE PMSPL PMVIOF PMWIN                                                        |
| Open32                                  | PMWINX MIRRORS REGISTRY                                                                                                                        |
| Intelligent Font Interface drivers      | PMATM TRUETYPE PMUNIF FREETYPE PMPRE                                                                                                           |
| Data Exchange                           | PMCLIP PMDDE PMDDEML                                                                                                                           |
| VDM PM interface                        | PMVDMH PMVDMP SEAMLESS SHIELD                                                                                                                  |
| WPS                                     | PMWP PMWPMRU PMVDDROP                                                                                                                          |
| Miscellaneous                           | PMPIC PMTKT MVDM                                                                                                                               |
| SOM API                                 | SOM SOMC                                                                                                                                       |





2016/07/25 02:16 · prokushev · 0 Comments

From:  
<http://cocorico.osfree.org/doku/> - **osFree wiki**

Permanent link:  
<http://cocorico.osfree.org/doku/doku.php?id=en:docs:os2:modules:viocalls&rev=1536076509>

Last update: **2018/09/04 15:55**

